

Lecture 10: February 25

*Lecturer: Prashant Shenoy**Scribe: Rufina Chettiar*

10.1 Communication

Assume there are two end points that want to communicate with each other. There are multiple intermediaries, such as nodes and routers. Also, there are OSs that implement the TCP/IP. There are a few characteristics of a communication.

- **Persistence:** Persistence means that the network is capable of storing messages for an arbitrary period of time until the next receiver is ready. Email and ground deliveries are good examples.
- **Transient:** Message is stored only so long as the next receiver is ready. For example, Transport-level communication discards the message if the process crashes for any reason. The system will not store the message.
- **Asynchronous:** Asynchronous communication means that the sender is doing non-blocking sending. It continues immediately after submitting the message.
- **Synchronous:** Synchronous communication blocks the process until the message is received or the sender gets a response from the server.

10.1.1 Persistent synchronous communication

The sender is blocked when it sends the message, waiting for an acknowledgement to come back. The message is stored in a local buffer, waiting for the receiver to run and receive the message. Some instant message applications, such as Blackberry messenger, are good examples. When you send out a message, the app shows you the message is "delivered" but not "read". After the message is read, you will receive another acknowledgement.

10.1.2 Transient asynchronous communication

Since the message is transient, both entities have to be running. Also, the sender doesn't wait for responses because it is asynchronous. UDP is an example.

10.1.3 Receipt-based transient synchronous communication

The acknowledgement sent back from the receiver indicates that the message has been received by the other end. The receiver might be working on some other process.

10.1.4 Delivery-based transient synchronous communication

The acknowledgement comes back to the sender when the other end actually takes control of the message. Asynchronous RPC is an example.

10.1.5 Response-based transient synchronous communication

The sender blocks until the receiver processes the request and sends back a response. RPC is an example. There is no clean mapping of TCP to any type of communication. From an application standpoint it maps to transient asynchronous communication. However, in a protocol standpoint, it maps to a receipt-based transient synchronous communication if it only has a one-size window.

10.2 Message-oriented Persistent Communication

This section explains what kind of middleware is required to perform persistent communication.

10.2.1 Message queuing system

The persistent queue exists between the sender and the receiver. It takes messages from the sender and passes it down to the receiver whenever it is ready. It's a queue that is stored on disks, so you can store the message for an arbitrary amount of time. There are more than one persistent queue between the end points. However, there is no guarantee that messages will be read. There are four abstract methods needed to implement a message queuing system.

- **put: append message to the queue**
- **get: get the message from the queue**
- **poll: poll to see if the queue is empty or not**
- **notify: notify the sender when the message is put into the queue**

In a more general architecture, there are usually many queues in the middle. There are application-level routers that implements the message queuing system. Messages will be delivered hop by hop, and they will be queued until the next receiver is ready.

IBM WebSphere MQ is a example of message queuing system. This is a middleware which compose of queue managers, which manages the queue, and a channel agent, which manages the packet transportation. There are also other open source MQSs. If disks that act as persistent queues only have finite capacity, there should be a policy deciding how long are the messages queued. Email, for example, queues the mail for a certain amount of time before the receiver is available.

10.2.2 Message Brokers

It transforms messages to the form that is needed. It can also be used as a filter. This is used in pub-subsystems. The receiver could subscribe to a certain type of message, and when the message arrives at the broker, it filters the message interested to the subscriber.

10.3 Stream-Oriented Communication

Audio and video streaming are good examples of stream-oriented communication. You send the video file in smaller pieces, and you have to send them continually in time. There are timing constraints to assure good performance, which do not exist in message-oriented communication. Late data are actually not much use. An important characteristic is isochronous communication. There are timeliness constraints in stream-oriented communication. The network has to deliver data on time, or the users don't get satisfactory performance. Another characteristic is that this type of communication is server-push. There are no explicit request for data from the user. The streaming server continues to send data to the client, and the client simply keeps listening on the socket and receiving data. There are also client-pull streaming systems as well.

There are two classes of streaming depending on what type of data:

- **Stored data streaming**
- **Live Streaming**

Skype is an example of live streaming, and youtube is an example of stored data streaming. Live streaming has even more stringent constraints, because people have lower tolerance of lag in live streaming. There could be multiple receivers for one source, which can be done by a mechanism called multicast. Live stream of a sporting event is an example of multicast.

10.4 Streams and Quality of Service

The application is demanding a certain level of quality. The network and end system should meet these some requirements or the quality of service will not be satisfied. Bandwidth, delay, and lost constraints are examples of possible demands.

Early streaming system are built on UDP because data retransmission of TCP causes more problem in streaming. Nowadays, modern systems use TCP protocol to stream. Quality of video is another requirement of quality of service. For example, on youtube allows you could set the playback quality of the video. Moreover, It can estimate online the quality of packet streaming. If the system sees a lot of lost packets, it will lower the quality of the video. The system could have requirements on jitters, which is the variance of the delay. Bandwidth could be either fixed bandwidth or variant bandwidth.

There are two kinds of encoding scheme:

- **Fixed rate encoding**
- **Variable rate encoding**

In these, the encoding rates could vary depending on the encoded data. In the old days, People assume that when the server starts streaming, it would tell the network the requirements it needs to have a satisfactory streaming, then the network would reserve resources for this stream. This is not implemented nowadays because it is difficult for the network to guarantee to provide resources. However, QOS is still needed.

10.4.1 Token bucket

One mechanism to enforce constraint on bandwidth is the token bucket, or leaking bucket. It is also called the policing mechanism. Token bucket is an OS level mechanism. You could attach it to applications or

a socket end points to enforce a constraint on the end point. You specify two parameters for the bucket: rate r and burst b , and this mechanism guarantees that the transmission rate does not exceed r . Once in a while, you can send a burst b of packets. The amount of data you can send at a time t is bounded by the equation: $r*t+b$. When you start the token bucket system, there are b tokens in the bucket. Every time an application generates a packet, it has to grab a token before it enters the network. Every second you generate r new tokens and add them into the bucket. The bucket can hold a maximum of b tokens. If the bucket is empty, no packets could pass. If an application requires rate r and burst b from the network, this mechanism restricts the application to meet the requirements it specified itself.